

## Create a rule to move messages after they have been read.

To create a message to move messages after they have been read to another folder, start by by opening the Auto-Mate Rule Manager window:



Then click the New button to create a new rule:



Give the rule a name, and select the following options on the **Rule Basics** tab:

Auto-Mate Rule Properties 🛛 🛛 🔀
Rule Name Move message after being read
Rule Basics Message Properties Actions Scheduling
Select how or when your rule should be applied Rule Types
Type: Scan messages after a period of time in a folder 🛛 🚽
Older Than: 1 hr
Source Folder: Inbox
1. Choose the following Rule type. 2. Select how long the messages should sit in the Inbox before getting moved. 3. Select the Inbox Folder.
Description
Scan messages after a period of time in a folder for the characteristics on the Message Properties tab, then apply the selected actions on the Actions tab.
Add Rule Cancel


Select the **Message Properties** tab:

lule Name Mov	e message after being read	_
Rule Basics Mes	sage Properties Actions Scheduling	
Only consider r	nessages that have the following properties	
Addressing		7
From	κ.	
To	د [ ]	
Co		
3		
Other properti	es	7
Subjec		
Message		
20000000 <del>0</del> 0	Select Status = Read	
Category		
Heade	C All 🔽	
Status		
Importance	Any Attachments: Ignore	
Flag Status	: Don't Care 🔽	
Message Size		-3
	Consider Size Greater than: 0 KB	
0		-8

Finally, select the Actions tab:

e Basics Messag	ge Properties Actio	ons	Scheduling	
	ng actions in seque	-		
Status	Set to Unread	~		
Importance	Set to Normal	~		
Flag Status	Follow-up Complet	e V		
Categories	Add To	v		
Subject	Prefix with	~		
Forward				
Reply	To Sender	v	Select the destination fo	der
	To Sender Text(.TXT)	~ ~	Select the destination for to move the messages	A CONTRACTOR OF
Reply				A CONTRACTOR OF
Reply     Export As	Text(.TXT) Detach/Save To	<ul><li></li></ul>		to
<ul> <li>Reply</li> <li>Export As</li> <li>Attachments</li> </ul>	Text(.TXT) Detach/Save To	<ul><li></li></ul>	to move the messages f	to
<ul> <li>Reply</li> <li>Export As</li> <li>Attachments</li> <li>Print</li> </ul>	Text(.TXT) Detach/Save To	<ul><li></li></ul>	to move the messages f	
<ul> <li>Reply</li> <li>Export As</li> <li>Attachments</li> <li>Print</li> <li>Copy To</li> </ul>	Text(.TXT) Detach/Save To hp psc 1310 series		PERGENEX-DT4)	
<ul> <li>Reply</li> <li>Export As</li> <li>Attachments</li> <li>Print</li> <li>Copy To</li> <li>Move To</li> </ul>	Text(.TXT) Detach/Save To hp psc 1310 series Old Mail		PERGENEX-DT4)	

The rule is now active to run. You can preview the messages that it will act upon by clicking on the rule, then right-clicking and selecting Preview. Preview will display a list of messages that the rule will move when it executes.



Article ID: 16

Last updated: 10 Apr, 2008

Revision: 1

Auto-Mate 3.x -> How to's -> Create a rule to move messages after they have been read.

http://www.pergenex.com/kb/index.php?View=entry&EntryID=16